

MODERN GEO




Create quilted modern art with this free pattern. Quilt design by Larene Smith featuring Supernova, a Hoffman Spectrum Digital Print panel designed by Jeanie Sumrall-Ajero. Shown with Me + You Indah Batiks.

BEGINNER



Citrine Colorway











P4287 232-Citrine 116 34-Eggplant

Free pattern available at www.hoffmanfabrics.com



MODERN GEO

Quilt design by Larene Smith featuring Supernova, a Hoffman Spectrum Digital Print panel designed by Jeanie Sumrall-Ajero. Shown with Me + You Indah Batiks.

61" x 67"

Yardage Chart

9		goonare
	FABRIC CITRINE COLORWAY	
Α	P4287 232-Citrine	1 panel
В	116 34-Eggplant	7/8 yard
С	113 461-Iron Gate	1 yard
D	101 494-Raven	1 3/4 yards
	FABRIC TOPAZ COLORWAY	
Α	P4287 238-Topaz	1 panel
В	110 92-Slate	7/8 yard
С	113 259-Lion	1 yard
D	103 632-Raw Umber	1 3/4 yards
	FABRIC ONYX COLORWAY	
Α	P4287 213-Onyx	1 panel
В	102 302-Stone	7/8 yard
С	100 21-Teal	1 yard
D	107 494-Raven	1 3/4 yards




Topaz Colorway



P4287 238-Topaz




110 92-Slate



113 259-Lion



103 632-Raw Umber



Onyx Colorway



P4287 213-Onyx



102 302-Stone



100 21-Teal



107 494-Raven

General Information and Instructions

- ➤ All seams are sewn with a 1/4" seam allowance.
- Pre-wash and press with spray starch before cutting.

- ➤ WOF = Width of Fabric.
- Press seams open as much as possible to decrease bulk.

Note: Read all the instructions before beginning. When cutting the fabric label each piece for the appropriate section for less confusion. Always refer to the illustration on the COVER as a guide when sewing the sections together.

Step 1 – Cutting the Fabric

1. Fabric A – Fussy cut the panel to measure 41" square – Sub-cut the Panel into TWO SECTIONS measuring 41" x 28-1/2" (Piece A) and 41" x 12-1/2" (Piece B) and sub-cut those pieces as follows:

Note: When cutting be sure to mark the TOP of the piece as this will help maintain the correct position of the fabric when sewn together.

- a. Piece A Sub-cut as follows:
 - i. (1) 24-1/2" x 28-1/2" rectangle Top Row Left Corner
 - ii. (6) 1-1/2" x 28-1/2" rectangles Top Row Middle
 - iii. (1) 6-1/2" x 28-1/2" rectangle Top Row Right Corner
- b. Piece B Sub-cut as follows:
 - i. (1) 24-1/2" x 12-1/2" rectangle Bottom Row Left Corner
 - ii. (6) 1-1/2" x 12-1/2" rectangle Bottom Row Middle
 - iii. (1) 6-1/2" x 12-1/2" rectangle Bottom Right Corner
- 2. Fabric B (Long Vertical) Cut (11) strips at 2-1/2" x WOF Sub-cut into (7) 2-1/2" x 28-1/2" rectangles (Top Row Middle), (7) 2-1/2" x 12-1/2" rectangles (Bottom Row Middle), and (7) 2-1/2" x 16-1/2" rectangles (Middle Row Middle).
- 3. Fabric C (Accent, Inner Border, and Binding) Cut (9) strips at 1-1/2" x WOF Sub-cut as follows:
 - a. Pull (3) strips and cut (6) 1-1/2" x 16-1/2" (Middle Row Middle)
 - b. Sew the remaining (6) strips together at the 1-1/2" edge Sub-cut into (2) 1-1/2" x 56-1/2" rectangles (Left and Right Sides) and (2) 1-1/2" x 52-1/2" rectangles (Top and Bottom) Inner Border.
 - c. Cut (7) strips at 2-1/2" x WOF Join all the 2-1/2" edges for the binding.
- 4. Fabric D (Horizontal Section and Outer Border) Cut as follows:
 - a. Parallel to the SELVAGE cut (4) strips at 4-3/4" x 62" Sub-cut into (2) 58-1/2" x 4-3/4" rectangles (Left and Right Sides) and (2) 61" x 4-3/4" rectangles (Top and Bottom) Outer Border.
 - b. From the remainder of the fabric cut (1) 24-1/2" x 16-1/2" rectangles (Middle Row Right) and (1) 6-1/2" x 16-1/2" rectangle (Middle Row Left).

Step 2 – Top Row

- 5. Sew the following pieces together at the 28-1/2" edge from left to right as follows to measure 50-1/2" $\times 28-1/2$ " Label "Top Row" and set aside for use later.
 - a. Fabric A 24-1/2", Fabric B 2-1/2", Fabric A 1-1/2", Fabric B 2-1/2", Fabric A 1-1/2", Fabric B 2-1/2", Fabric A 1-1/2", Fabric B 2-1/2", Fabric B 2-1/2", Fabric A 1-1/2", Fabric B 2-1/2", Fabric A 1-1/2", Fabric B 2-1/2", Fabric A 1-1/2", Fabric B 2-1/2".

Step 3 - Middle Row

- 6. Sew the following pieces together at the 16-1/2" edge from left to right as follows to measure 50-1/2" x 16-1/2" Label "Middle Row" and set aside for use later.
 - a. Fabric D 24-1/2", Fabric B 2-1/2", Fabric C 1-1/2", Fabric B 2-1/2", Fabric C 1-1/2", Fabric B 2-1/2", Fabric C 1-1/2", Fabric B 2-1/2", Fabric D 6-1/2".
- 7. Sew the Middle Row to the bottom of the Top Row at the 50-1/2" edge to measure 50-1/2" x 44-1/2" Label "Middle Row" and set aside for use later.

Step 4 – Bottom Row

- 8. Sew the following pieces together at the 12-1/2" edge from left to right as follows to measure 50-1/2" x 12-1/2" Label "Top Row" and set aside for use later.
 - a. Fabric A 24-1/2", Fabric B 2-1/2", Fabric A 1-1/2", Fabric B 2-1/2", Fabric A 1-1/2", Fabric B 2-1/2", Fabric A 1-1/2", Fabric B 2-1/2", Fabric B 2-1/2", Fabric A 1-1/2", Fabric B 2-1/2", Fabric A 1-1/2", Fabric B 2-1/2", Fabric A 1-1/2", Fabric B 2-1/2".
- 9. Sew the Bottom Row to the bottom of the Middle Row to finish the CENTER of the quilt at 50-1/2" x 56-1/2".

Step 5 – Adding the Borders

- 10. Inner Border Sew (1) Fabric C 1-1/2" \times 56-1/2" rectangle to the left and right sides, then sew (1) Fabric C 52-1/2" \times 1-1/2" rectangle to the top and bottom to finish the Inner Border at 52-1/2" \times 58-1/2".
- 11. Outer Border Sew (1) Fabric D 4-3/4" x 58-1/2" rectangle to the left and right sides, then sew (1) Fabric D 61" x 4-3/4" rectangle to the top and bottom to finish the quilt top at 61" x 67".

Step 6 – Finishing the Quilt

- 12. Layer the backing, batting, and quilt top and quilt as desired.
- 13. Using Fabric C 2-1/2" strips sew on the binding to finish the quilt.