

# BASIC Pillowcases

(Uses a Large Panel)



**Fabric A - Customers Choice**  
**Main Body**  
 2/3 yard (24" panel)

**Fabric B - Customers Choice**  
**Cuff & Closed end**  
 5/8 yard



# BASIC Pillowcases (Uses A Large Panel)

Please read all instructions carefully AND identify all fabrics before beginning.

All instructions include a 1/4" seam allowance unless stated otherwise and strips are cut selvage to selvage (WOF).

## 1. Cut the following:

*Do not trim selvages from strips until directed.*


**Fabric A** - Cut 1 panel 22" x WOF

**Fabric B** - Cut (1) 11" x WOF strip (cuff)


Cut (1) 6-1/2" x WOF strip

## 2. Piecing Order:


1. With wrong sides together and a 1/4" seam allowance, sew **Fabric B** 6-1/2" x WOF strip lengthwise to left side of **Fabric A** panel. Trim seam to 1/8" then press open. Fold **Fabrics A** and **B** pieces right sides together along the seam. Stitch again with a 1/4" seam allowance enclosing the first seam. Press seam allowance to **Fabric B** and topstitch down.



2. Place **Fabric B** 11" x WOF cuff, right side up, on a flat work surface with long edges on sides. Place **Fabrics A/B** piece, right side down, panel edge centered on right edge of **Fabric B** piece, with long edges aligned. Pin layers together on right edge.



3. Starting on the left edge of **Fabrics A/B** piece, roll **Fabrics A/B** piece up into a tube until at least 6" of **Fabric B** cuff is exposed.



*Shading of diagrams may vary depending on fabrics used.*

*Letters in italics and pieces shown dotted indicate wrong side of fabric.*

4. Fold the left edge of the cuff to the right and over the rolled tube of **Fabrics A/B** to meet the right edge of the fabrics. Align all width-of-fabric edges along the right edge. Match the selvage edges of the top and bottom edges of the **Fabric B** piece.




Pin all layers together being careful to avoid pinning the rolled tube.

5. Stitch through all layers on pinned edge with a 1/4" seam allowance.



Be careful not to stitch the rolled fabric in the seam. Backstitch at both ends of seam.

6. Grasp the rolled up **Fabrics A/B** piece from inside 1 end of the tube.




Pull it firmly until the **Fabric**



**B** cuff is turned right side out. Press the seam flat. If desired, topstitch or sew a decorative stitch over the seam.

7. Trim selvage/uneven edges on both sides of the pillowcase. It will be 42"-44" wide.



8. Fold pillowcase, *right side out*, so it is 21" - 22" wide. With a 1/4" seam, sew the unfolded side and bottom, aligning raw edges. Trim seam allowance to 1/8" and clip corners. Turn pillowcase, *wrong side out*. Press seam flat. Stitch sewn side and bottom edges again with a 1/4" seam enclosing the first seam. Turn right side out. Press flat. Enjoy!

