




Cutting



A	(4) 2" squares. Grunge #30150 101
B	(4) 4 ¼" squares; cut each square twice diagonally to make (16) B triangles. Grunge #30150 101
C	(16) 2 ⅜" squares; cut each square once diagonally to make (32) C triangles. Grunge #30150 82
D	(4) 3 ½" squares. Grunge #30150 327
E	(1) 3 ½" square. Grunge #30150 101
F	(4) 2" x 3 ½" rectangles. Grunge #30150 101






Cut Square Once
Diagonally







Cut Square Twice
Diagonally

Assembly

1. Begin block assembly by creating flying geese units. Place (1) C triangle on either side of (1) B triangle as shown.
2. Sew the C triangles to the B triangle one at a time using a scant ¼" seam. Press toward the corners.
3. Trim large flying geese units to measure 2" x 3 ½" unfinished. Repeat to make (16) identical flying geese units.



4. Continue block assembly by laying out all flying geese units, (4) A squares, (4) B rectangles, (4) D squares, (1) E square, and (4) F rectangles as shown. Begin assembling the block in (5) horizontal rows. Arrows indicate pressing instructions.
5. Sew all horizontal rows together to complete block assembly. Press. Block should measure 12 ½" x 12 ½" unfinished.



Be sure to share your block and progress online!

#ModaStitchPink

