

Rhythm & HUES Quilt



Featuring the Rhythm &
Hues Collection
by Connie Haley
Shipping to stores July 2021!

Finished Size: 48 ½" x 48 ½" (123.19cm x 123.19cm)

Fabric Needed

3 Wishes® Rhythm & Hues Collection

- 1 Panel – Record Panel (18003-MLT-CTN-D)
- 1 yard – Allover Records (18001-MLT-CTN-D)
- ¾ yard – Piano Keys (17997-WHT-CTN-D)
- ½ yard – Music Words (18004-MLT-CTN-D) for Piecing and Binding
- ½ yard – Color Vibe (17996-MLT-CTN-D)
- ½ yard – Music Notes (18000-MLT-CTN-D)
- 2 ½ yards – Instruments (18002-WHT-CTN-D) for Backing

Additional Supplies Needed:

- 57" x 57" (144.78cm x 144.78cm) Cotton batting
- Piecing and sewing thread
- Quilting and sewing supplies
- Even-feed foot (optional for quilting)

Before You Begin

Read all instructions before beginning project. Do not pre-wash fabrics. Press fabrics with a dry iron on cotton setting before cutting. Use a ¼" (6.35mm) seam allowance and sew fabrics with right sides together (RST) unless otherwise noted. Press seams in the direction of the arrows. wof = width of fabric

Cutting

Use a rotary cutter and acrylic ruler to cut the number of pieces from each fabric listed below.




Record Panel (18003-MLT-CTN-D) 1 Panel
Fussy Cut 1 – 34" x 34" (86.36cm x 86.36cm)



Allover Records (18001-MLT-CTN-D) 1 Yard
Fussy Cut 4 – 3 ½" x 36 ½" (8.89cm x 92.71cm)
Fussy Cut 4 – 3 ½" x 3 ½" (8.89cm x 8.89cm)


3 ½"
x
3 ½"



Piano Keys (17997-WHT-CTN-D) ¾ Yard
Fussy Cut 4 – 3 ½" x 36 ½" (8.89cm x 92.71cm)




Music Words (18004-MLT-CTN-D) ½ Yard
Cut 5 – 2 ½" (6.35cm) x wof (Binding)
Cut 4 – 3 ½" x 3 ½" (8.89cm x 8.89cm)



Color Vibe (17996-MLT-CTN-D) ½ Yard
Cut 2 – 1 ¾" x 36 ½" (4.44cm x 92.71cm)
Cut 2 – 1 ¾" x 34" (4.44cm x 86.36cm)

3 ½"
x
3 ½"



Music Notes (18000-MLT-CTN-D) ½ Yard
Fussy Cut 8 – 3 ½" x 3 ½" (8.89cm x 8.89cm)


Sewing

Note: Check orientation of fabrics.


1. Place a Color Vibe strip (1 $\frac{3}{4}$ " x 34") on each side of the Fussy Cut Record Panel 34" x 34" (86.36cm x 86.36cm) as shown in Diagram A. Pin RST, sew and press. Place a Color Vibes strip 1 $\frac{3}{4}$ " x 36 $\frac{1}{2}$ " (4.45cm x 92.71cm) on the top and bottom. Pin RST, sew and press to make the Quilt Center 36 $\frac{1}{2}$ " x 36 $\frac{1}{2}$ " (92.71cm x 92.71cm).




2. Place one Fussy Cut Allover Records, one Music Words and two Fussy Cut Music Notes squares 3 $\frac{1}{2}$ " x 3 $\frac{1}{2}$ " (8.89cm x 8.89cm) in two rows as shown in Diagram B. Pin the squares in each row RST, sew and press. Pin the rows RST matching seams, sew and press to make the Top Left Corner 6 $\frac{1}{2}$ " x 6 $\frac{1}{2}$ " (16.51cm x 16.51cm).




3. Follow Step 2 and Diagram C to make the Top Right, Bottom Left and Bottom Right Corners 6 $\frac{1}{2}$ " x 6 $\frac{1}{2}$ " (16.51cm x 16.51cm).




4. Place one Fussy Cut Piano Keys and one Fussy Cut Allover Records rectangle 3 $\frac{1}{2}$ " x 36 $\frac{1}{2}$ " (8.89cm x 92.71cm) as shown in Diagram D. Pin RST on the long edges, sew and press to make the Left Side Border 6 $\frac{1}{2}$ " x 36 $\frac{1}{2}$ " (16.51cm x 92.71cm).




5. Follow Step 4 and Diagram E to make the Right Side Border 6 $\frac{1}{2}$ " x 36 $\frac{1}{2}$ " (16.51cm x 92.71cm).



6. Follow Step 4 and Diagram F to make the Top Border Center $6\frac{1}{2}" \times 36\frac{1}{2}"$ (16.51cm x 92.71cm). Place the Top Left and Right Corners $6\frac{1}{2}" \times 6\frac{1}{2}"$ (16.51cm x 16.51cm) on each side as shown. Pin RST, sew and press to make the Top Border $6\frac{1}{2}" \times 48\frac{1}{2}"$ (16.51cm x 123.19cm).




7. Follow Step 4 and Diagram G to make the Bottom Border Center $6\frac{1}{2}" \times 36\frac{1}{2}"$ (16.51cm x 92.71cm). Place the Bottom Left and Right Corners $6\frac{1}{2}" \times 6\frac{1}{2}"$ (16.51cm x 16.51cm) on each side as shown. Pin RST, sew and press to make the Bottom Border $6\frac{1}{2}" \times 48\frac{1}{2}"$ (16.51cm x 123.19cm).



8. Place the Quilt Center $36\frac{1}{2}" \times 36\frac{1}{2}"$ (92.71cm x 92.71cm), Left and Right Side Borders $6\frac{1}{2}" \times 36\frac{1}{2}"$ (16.51cm x 92.71cm) and the Top and Bottom Borders $6\frac{1}{2}" \times 48\frac{1}{2}"$ (16.51cm x 123.19cm) as shown in Diagram H. Pin the Sides to the Center, RST matching ends and middle, sew and press. Pin the Top and Bottom, RST matching ends, middle and seams, sew and press. The Rhythm & Hues Quilt Top should measure $48\frac{1}{2}" \times 48\frac{1}{2}"$ (123.19cm x 123.19cm).




9. Remove the selvages from the Instruments Backing fabric. **Note:** Check orientation of fabrics. Cut one piece 40 1/4" x 57" (102.24cm x 144.78cm) and two pieces 17 1/4" x 28 3/4" (43.82cm x 73.03cm). Pin the two smaller pieces RST on the short edges and sew; press. Pin the two sections RST and sew along the long edges as shown in Diagram I. Press seams open or to one side. The Backing should measure 57" x 57" (144.78cm x 144.78cm).



Finishing

10. Press finished Quilt Top and Backing. Tape the Backing, **wrong** side up, to a firm surface. Layer Batting and Quilt Top (right side up). Baste the layers together with safety pins. Quilt as desired.
11. Once quilting is complete, square up corners and edges, trimming excess Backing and Batting even with the Quilt Top.
12. Follow Diagram J to make the Music Words Binding. Remove selvages and sew the short ends of the five 2 1/2" x wof strips RST end to end at a 45° angle to make one continuous strip; press seams open. Press one short end 1/4" to the **wrong** side. Fold in half lengthwise with **wrong** sides together; press. Leaving a 2" (5.08cm) tail on the folded end, place cut edges of folded Binding even with the edge of the Quilt Top and sew, mitering the corners. Overlap ends, trim any excess and finish sewing the Binding. Fold Binding over to back and hand stitch.

Dia. J



Finished Care Instructions

Machine wash in cold water; gentle cycle. Do not bleach. **Tip:** Before drying, check for fabric dyes that may have run. If fabric dyes run, rewash and rinse using a color catcher to absorb loose dye. Lay flat to dry or tumble dry low.