






Fabric and Supplies Needed

Fabric amounts based on yardage that is 42" wide.

Color	Fabric	Name/SKU	Yardage	Color	Fabric	Name/SKU	Yardage
	A	AQM-15952-267 ADVENTURE	2/3 yard (one panel)		D	AQM-15949-155 STONE	1-1/4 yard
	B	AQM-15949-169 EARTH	1-1/3 yard		E	AQM-15953-267 ADVENTURE	1/3 yard
	C	AQM-15949-13 TAN	1/3 yard	You will also need: 3 yards for backing			
Copyright 2016, Robert Kaufman For individual use only - Not for resale							

Notes Before You Begin

- Read through all of the instructions before beginning.
- All of the seam allowances are 1/4" unless otherwise noted.
- Press seam allowances open unless otherwise noted.
- Width of fabric (WOF) is equal to at least 42" wide.
- Right sides together has been abbreviated to RST.
- Remember to measure twice and cut once!

Cutting Instructions

Fabric A

Fussy cut eight panel blocks to 9-1/2" x 11"

Fabric B

Cut ten strips 1" x WOF

sub cut four strips into sixteen 1" x 9-1/2" strips

sub cut six strips into sixteen 1" x 12" strips

Cut one strip 3-1/2" x WOF

Cut seven strips 2-1/2" x WOF - set six strips aside for binding

Cut six strips 1" x WOF

Cut one strip 1-1/2" x WOF

Fabric C

Cut two strips 1-1/2" x WOF

Cut four strips 1-1/4" x WOF

Fabric D

Cut nine strips 1-1/2" x WOF

trim two strips down to 1-1/2" x 40-1/2"

Cut six strips 1-1/4" x WOF

Cut three strips 2-1/4" x WOF

Cut four strips 2-1/2" x WOF

sub cut four strips into sixteen 2-1/2" x 10-1/2" strips

Fabric E

Cut two strips 5" x WOF

trim down to 5" x 40-1/2"

Bordering the Panel Blocks

Step 1 Sew a 1" x 9-1/2" Fabric B strip to the top and bottom of each Fabric A panel block. Press seams toward Fabric B.

Step 2) Sew a 1" x 12" Fabric B strip to the left and right sides of the panels from Step 1. Press seams toward Fabric B. Repeat to make eight 10-1/2" x 12" panel blocks.





Making the Strip Pieced Units (SPU)

Step 3 Gather two 1" x WOF Fabric B Strips, one 1-1/2" x WOF Fabric B strip, two 1-1/4" x WOF Fabric C strips, and four 1-1/2" x WOF Fabric D strips. Sew strips together in the order shown. Press all seams in same direction.


Step 4 Cut strip set from Step 3 into sixteen 2-1/4" strips. See dashed lines in diagram at right. You will be able to get all eight strips out of the strip set even though the diagram does not show it. Label as SPU1 and set aside.

Step 5 Gather two 1" x WOF Fabric B strips, one 2-1/2" x WOF Fabric B strip, two 1-1/4" x WOF Fabric C strips, and four 1-1/4" x WOF Fabric D strips. Sew strips together in the order shown. Press all seams in same direction. Label as SPU2.

Step 6 Cut strip set from Step 5 into sixteen 2" strips. Label as SPU2 and set aside.



Step 7 Gather two 1" x WOF Fabric B strips, one 3-1/2" x WOF Fabric B strip, two 1-1/4" x WOF Fabric C strips, and two 1-1/2" x WOF Fabric D strips. Sew strips together in the order shown. Press all seam in same direction. Label as SPU3.



Step 8 Cut strip set from Step 7 into eight 4" strips. Label as SPU3 and set aside.

Step 9 Sew a SPU2 block to either side of a SPU3 block. See fig. 1. Press all seams in the same direction.

Step 10 Sew an SPU1 block to either side of the block from Step 9. See fig. 2. Press seams in the same direction as step 9. Unit should measure 8" x 10-1/2".

Step 11 Sew a 2-1/2" x 10-1/2" Fabric D strip on the top and bottom of the block from Step 10. See fig. 3. Press all seams in same direction. Repeat to make eight 10-1/2" x 12" strip pieced blocks.




fig. 1




fig. 2





fig. 3

Putting Together the Quilt Top



Step 12 Arrange the blocks together in four rows of four blocks each, alternating panel blocks and strip pieced blocks and following the Quilt Assembly Diagram. Sew the blocks together to form rows, pressing the seams to the left in odd numbered rows and to the right in even numbered rows. Sew the rows together, nesting the seams and pressing the row seams open.

Step 13 Sew a 1-1/2" x 40-1/2" Fabric D strip to the top and bottom of the quilt top. Press toward Fabric D.

Step 14 Sew a 5" x 40-1/2" Fabric E strip to the top and bottom of the quilt top. Press toward Fabric E.

Step 15 Sew three 1-1/2" x WOF Fabric D strips together, end-to-end. From the resulting strip cut two strips 1-1/2" x 57-1/2". Sew to the left and right sides of quilt top. Press toward Fabric D.

Step 16 Sew three 2-1/4" x WOF Fabric D strips end to end. From the resulting strip cut two strips 2-1/4" x 42-1/2". Sew to the top and bottom of quilt top. Press toward Fabric D.

Finishing the Quilt

Step 17 Cut backing fabric into two pieces 1-1/2yds x WOF. Sew together along selvedge edge, press seam, and trim as desired.

Step 18 Layer your backing face down, then batting, then your quilt top face up.

Step 19 Baste through all layers, then quilt as desired. Bind using Fabric B.